



# Projetex 3D Server

INSTALLATION AND SETUP GUIDE

## Index

Disclaimer .....	2
System Requirements .....	2
Registration / Upgrade .....	3
Trial Period .....	3
Purchase information .....	3
Registering/Upgrading Projetex Server Administrator software .....	4
Projetex Server Administrator Setup .....	5
Access to Projetex Server Administrator .....	7

# Disclaimer

Although every precaution has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document or from the use of programs and source code that may accompany it. In no event shall the publisher and the author be liable for any loss of profit or any other commercial damage caused or alleged to have been caused directly or indirectly by this document.

Projetex and AnyCount are registered trademarks of [Advanced International Translations, Ltd.](#)

## System Requirements

Hardware and Software	
<b>Operating System</b>	Microsoft Windows 7 Microsoft Windows 8.1 Microsoft Windows 10 Microsoft Windows Server 2008 Microsoft Windows Server 2012 Microsoft Windows Server 2016
<b>CPU</b>	1GHz or faster 32-bit (x86) or 64-bit (x64) processor
<b>Memory</b>	2GB (at least 4GB is recommended)
<b>Hard Disk Space for Installation</b>	More than 2GB for the application
<b>Other</b>	Internet connection for product activation LAN, VPN or Internet connection to contact Projetex Server remotely Microsoft .NET Framework 4 or later

 **NOTE:** *It is important to have enough space for database (at least 100–200 MB at any given moment) so that it grows naturally without any problems and errors due to insufficient hard drive space.*

# Registration / Upgrade

## Trial Period

You are welcome to use [Projetex](#) free of charge during evaluation period of **30 days**.

During the evaluation period [Projetex](#) is fully functional, with the following limitations:

- Number of **clients** can be no more than **40**;
- Number of **prospects** can be no more than **40**;
- Number of **projects** can be no more than **50**;
- Number of **freelancers** can be no more than **20**;
- Number of **applicants** can be no more than **20**;
- Number of **corporate experts** can be no more than **30**;
- Embedded **AnyCount** engine works with trial limitations.

## Purchase information

After purchasing of [Projetex Server](#) and [Workstation](#) applications, you will receive an e-mail message containing your serial numbers for [Projetex Server](#) and [Projetex Workstations](#).

Before registering your [Projetex Workstations](#) you need to register your [Projetex Server](#).

-  **NOTE:** *If you are a user of earlier Projetex versions, be sure to order special Upgrade Projetex 3D License. The cost of such license is much lower than the cost of Base Projetex 3D License. Please visit our website for prices.*
-  **NOTE:** *Registration implies entering the serial numbers to the activation windows of Projetex applications (thus switching off the evaluation mode and removing evaluation period limitations).*
-  **NOTE:** *As your business grows you may need to register more Projetex Workstations. To do so, order the license upgrade and register again your Projetex Server Administrator and the necessary number of Workstations.*

You can order the License Upgrade from the following web page:

<https://projetex.com/order-translation-project-management-tool/more-workstations>

[Projetex Licenses](#) differ by type and by the number of Workstations foreseen in it.

**Maximum number of Workstations** determines how many [Workstations](#) can connect to [Projetex Server](#) at any given moment. Number of Workstations in your [Projetex license](#) does not limit the number of [Workstations](#) installed.

Projetex Licenses can be of one of the following types:

License type	Description
<b>Base Projetex 3D License</b>	Projetex 3D Base License determines the number of workstations which can concurrently connect to Projetex Server. It includes Projetex Server license.
<b>Upgrade to Projetex 3D License</b>	<p>Upgrade from earlier version of Projetex to Projetex 3D License must be purchased by any users of earlier versions, who wish to transfer to Projetex 3D.</p> <p>The price of Upgrade from Projetex to Projetex 3D License is much lower than the price of Base Projetex 3D License.</p> <p>Be sure to order this license for the same total number of Workstations as in your earlier Projetex license.</p>
<b>Upgrade License</b>	<p>This license allows company management to enable access for greater number of workstations to the existing Projetex Server and, thus, to your Projetex Database.</p> <p>This is useful when you already use Projetex 3D and your business grows.</p>

After your order is processed you will receive upgraded [Projetex Server](#) serial number and upgraded [Projetex Workstation](#) serial number.

## Registering/Upgrading Projetex Server Administrator software

1. Run [Projetex Server Administrator](#).
2. Click menu **Register** (or **Upgrade**) button on the **Database Server** tab or in **Help** menu of installed [Projetex Server Administrator](#) application.
3. Paste your [Projetex Server serial number](#), which you will receive by email, into *Activation* window of [Projetex Server Administrator](#) and click **Unlock**.

# Projetex Server Administrator Setup

To install and set-up Projetex Workstation, please follow these steps:

1. **Download Projetex Setup file** using the following link:

<https://cf.projotex.com/downloads/Projotex3DSetup.exe>

2. **Run the downloaded setup file and** proceed with the **Setup Wizard** steps.

During the installation procedure **Projotex Setup** will prompt you to select components to install.

 **NOTE:** To quickly select only Projotex Server or Projotex Workstation components, use dropdown list and select Server Installation option or Workstation Installation option correspondingly.

- 2.1. **Projotex Server** — Projotex server and desktop application used to control the server.

Select this check box if you need to set up **Projotex** database on the current PC.

- 2.2. **Microsoft SQL Server 2014 Express** – leave this checkbox set, if you install **Projotex Server** for the first time. Un-check the checkbox, if **Projotex Server** is already installed or you would like to use another existing instance of **Microsoft SQL Server** with **Projotex 3D** (advanced users only).

- 2.3. **Demo Database.** Select this option if you are installing Projotex for evaluation. This database contains some sample records, imitating the workflow data of a translation agency. This option can also be used for initial server sub-system setup if you re-install Projotex Server on another computer and plan to restore your existing database afterwards.

- 2.4. **Empty database.** Select this option to install clean database before you begin entering your actual workflow data to Projotex.

- 2.5. **Do not install database.** Select this option in case you are just updating your System Administrator software, and you already have your database up and running and there is no need to install another one. **Microsoft SQL Server** setup will be skipped if you select this option.

- 2.6. **Projotex Automation Service, Projotex Auto Backup Service, Projotex Database Upgrade Utility** – set these checkboxes to install utilities respectively or remove the check to skip the installation of the utility.

For instructions regarding these utilities please refer to corresponding manuals.

 **NOTE:** As a security measure, Projotex Server Setup under no circumstances will overwrite existing database. If you would like to install new database, please remove or delete existing database file manually before running Projotex Setup.

3. After installation completes, run **Projotex Server Administrator** and register your Projotex.

Your [Projetex License](#) will not limit the number of installed workstations. Only the number of [Projetex Workstations](#), which can connect to [Projetex Server](#) simultaneously, is limited by the number of users (workstations) in your license.

 **NOTE:** *You need to register your [Projetex Server](#) before registering your [Projetex Workstations](#).*



# Access to Projetex Server Administrator

Access to [Projetex Server Administrator](#) is protected. You need to enter administrator password to access it.

Default login: [Admin](#)  
Default password: [admin](#)

Later you can add more users with some Administrator privileges. However, Admin account is somewhat special. You cannot remove Admin account, and it has fewer settings available than other accounts.

Administrative user account has ultimate access rights.

**NOTE:** *Administrators are advised to change password of admin account before entering any sensitive information to Projetex.*

To change the password for default admin account please do the following:

- Install and start [Projetex Workstation](#) application. You can install [Projetex Workstation](#) on the same computer where your [Projetex Server](#) is installed or on another computer.
- Start [Projetex Workstation](#) and sign into your Projetex Server using default admin account. Please refer to the corresponding guide for instructions.
- Open [Settings – Administrator – Users & Access](#) and find the user account whose login is 'Admin'.
- Double click the account and put the new password into the [Password](#) field. Please enter strong password to protect your information and Projetex settings from unauthorized access.